

Regulatory CS01 =

$$0.0001 \times t_i \times \exp\left(-\frac{s_i \times t_i}{LGD_{MKT}}\right) \times \left(\frac{EE_{i-1} \times D_{i-1} - EE_{i+1} \times D_{i+1}}{2}\right)$$

For the final time bucket $i = T$, the corresponding formula is

$$0.0001 \times t_i \times \exp\left(-\frac{s_i \times t_i}{LGD_{MKT}}\right) \times \left(\frac{EE_{i-1} \times D_{i-1} + EE_T \times D_T}{2}\right)$$

Regulatory CS01 =

(B) If the VaR model uses credit spread sensitivities to parallel shifts in credit spreads,

the [BANK] must calculate each credit spread sensitivity according to the following formula:

Regulatory CS01 =

$$0.0001 \times \sum_{i=1}^T \left(t_i \times \exp\left(-\frac{s_i \times t_i}{LGD_{MKT}}\right) - t_{i-1} \times \exp\left(-\frac{s_{i-1} \times t_{i-1}}{LGD_{MKT}}\right) \right) \times \left(\frac{EE_{i-1} \times D_{i-1} + EE_i \times D_i}{2}\right)$$